Create the ownCloud Database

Now that you have installed the prerequisites, it's time to create the ownCloud database and user. The commands in this section are issued from within the MariaDB console.

- 1. Access the MariaDB console:
- 2. sudo mysql -u root -p
- 3. create your ownCloud database:
- 4. CREATE DATABASE ownclouddb;
- 5. Create a new user with the necessary privileges, including a strong and unique password. Be sure to substitute PASSWORD with your own password:

```
>CREATE USER 'ownclouduser'@'localhost' IDENTIFIED BY 'letmein'; >GRANT ALL ON ownclouddb.* TO ''ownclouduser'@'localhost';
```

- 6. Flush your database's privileges:
- 7. FLUSH PRIVILEGES;
- 8. Finally, exit the database console:
- 9. exit

Download ownCloud

At this point, the system is ready for ownCloud. Before you actually download the software, check the <u>ownCloud downloads page</u> to confirm the most recent version.

- 1. Download ownCloud. As of writing this guide, the latest version is 10.5.0. Replace 10.5.0 with the version you want to download.
- 2. wget https://download.owncloud.org/community/owncloud-10.5.0.zip
- 3. Unzip the downloaded file:
- 4. unzip owncloud-10.5.0.zip

Note

If necessary, install unzip with the command:

```
sudo apt-get install zip -y
```

- 5. When you unzip the file, a new directory named owncloud is created. Move the new directory to the Apache document root. This example uses the default directory for Apache site files:
- 6. sudo mv owncloud /var/www/html/
- 7. Change the ownership of the owncloud directory:
- 8. sudo chown -R www-data: /var/www/html/owncloud

Create an Apache Configuration File

Apache requires a <u>virtual host configuration file</u> in order to server your ownCloud instance to the web.

- 1. Create an Apache configuration file using the Nano text editor:
- 2. sudo nano /etc/apache2/sites-available/owncloud.conf
- 3. Paste the following text into the new file. Replace mentions of example.com with your own domain name or your Linode's IP Address:

File: /etc/apache2/sites-available/owncloud.conf

- 1. Save and close the file by typing Ctrl + O and then, Ctrl + X:
- 2. Enable the rewrite, mime, and unique id Apache modules:
- 3. sudo a2enmod rewrite mime unique id
- 4. Restart the Apache server:
- 5. sudo systemctl restart apache2

The command line portion of the installation is complete.

Configure ownCloud

This section covers the web-based portion of the installation.

- 1. Open a web browser and navigate to your site's domain, if it has been configured to use a domain name like, http://example.com/owncloud. If you configured Apache to point to your server's IP address, navigate to http://192.0.2.0/owncloud and replace the example IP address with your own. You should see the ownCloud web-based installer.
- 2. Type a username and password for the admin user; click the Storage & Database drop-down; and then click MySQL/MariaDB.
- 3. The database information section is now available. Enter the following information:
 - o Database User: ownclouduser
 - o Database password: the password you set for the ownCloud database user
 - o Database: ownclouddb
 - o Localhost: leave as the default



4.	Click Finish setup . When the install completes, the ownCloud login page appears. Login with the newly-created admin credentials. Once logged in, you are taken to the main ownCloud page.